

ADVANCED
NAVIGATION

Orientus Manager Manual






Table of Contents

1	Revision History.....	2
2	Software Changelog.....	3
3	Introduction.....	4
3.1	System Requirements.....	4
3.2	Installation.....	4
3.3	Troubleshooting.....	4
3.3.1	All Platforms.....	4
3.3.2	Windows.....	4
3.3.3	Linux.....	4
4	Main View.....	5
4.1	Serial Port.....	5
4.2	Attitude Indicator.....	5
4.3	Status Indicator.....	5
5	Logging.....	6
6	Views.....	7
6.1	Device Information.....	7
6.2	Status.....	7
6.3	Raw Sensors.....	8
6.4	Orientation.....	9
7	Configuration.....	11
7.1	Sensor Ranges.....	11
7.2	Filter Options.....	12
7.3	Packet Rates.....	12
7.4	Alignment Configuration.....	13
7.5	Position.....	13
7.6	Baud Rates.....	13
7.7	GPIO Configuration.....	14
7.8	Reset.....	14
8	Tools.....	15
8.1	Terminal.....	15
8.2	Magnetic Calibration.....	15
8.3	Firmware Update.....	16
8.4	Log Converter.....	16



1 Revision History

Version	Date	Changes
1.1	21/02/2013	Initial Release



2 Software Changelog

Version	Date	Changes
1.1	21/02/2013	Initial Release



3 Introduction

Orientus Manager is a cross platform software tool for testing, configuration and logging of Orientus. It is designed to be simple and easy to use.

3.1 System Requirements

Orientus Manager has reasonably low system requirements and most computers from 2005 onwards should have no problem running Orientus Manager.

When Orientus is running at very high output rates e.g. 1000 Hz, Orientus Manager can consume significant system resources handling the large quantities of data.

3.2 Installation

Orientus Manager does not need to be installed and can be run from any directory by double clicking on it. Orientus Manager requires a recent version of Java, available at <http://www.java.com>. On some systems to open the program it may be necessary to right click and select open with → Java Runtime Environment.

Both the Orientus evaluation kit and the Orientus OEM development kit make use of an FTDI USB device. The drivers are normally installed automatically, if not they are available from <http://www.ftdichip.com/Drivers/VCP.htm>.

3.3 Troubleshooting

Please contact support@advancednavigation.com.au if you are having issues.

3.3.1 All Platforms

If Orientus Manager will not start, ensure you have Java installed.

3.3.2 Windows

There is a well known problem with USB serial devices under Windows known as “crazy mouse”. The problem occurs when the system mistakenly installs the USB serial device as a mouse. Unfortunately Microsoft has not fixed this problem in over 15 years, so it probably won't be fixed. If you experience this problem, often a restart will resolve it. Otherwise there is a tool available at <http://www.stentec.com/anonftp/pub/wingps/pnpblockersetup.exe> that can fix the issue.

If the serial port does not show up when you plug in your Orientus USB device, you may need to install the drivers from <http://www.ftdichip.com/Drivers/VCP.htm>.

If you experience a blue screen of death whilst using Orientus Manager, this is typically a problem associated with older FTDI drivers. To resolve the problem, install the latest drivers from <http://www.ftdichip.com/Drivers/VCP.htm>.

3.3.3 Linux

If serial ports do not show up, the typical cause is permissions. The user should add themselves to the dialout group with the command `sudo adduser username dialout`.



4 Main View




Illustration 1: Screenshot of Orientus Manager main view

4.1 Serial Port

The serial port dialog is used to connect to Orientus. You should select a serial port and baud rate then click connect. The default baud rate of Orientus is 115200. The connection indicator displays whether there is communication with an Orientus unit.

4.2 Attitude Indicator

The aircraft style attitude indicator shows roll and pitch through a virtual horizon. Heading is shown at the top. The units are degrees.

4.3 Status Indicator

This indicator shows any problems with Orientus. Once the filter has initialised it should show "Healthy". Clicking on the indicator will show the detailed status flags.



5 Logging

Orientus Manager features a fully automatic logging system. Every time the serial port connect button is clicked Orientus Manager starts a new log file in either the current directory or the user's home directory. The log file is given the file name OrientusLog_date_time.anpp and contains all of the raw data received from Orientus in the AN packet protocol. The log files are closed when the serial port is disconnected. To convert these log files into easily accessible formats, the log converter dialog in the tools menu can be used, see section 8.4. The log converter dialog creates a folder and generates files in the CSV (comma separated values) format that can be easily opened with Microsoft Excel, Openoffice, Matlab and most other data analysis programs.

▼	Folder	OrientusLog_13-02-14_16-12-25	Today 12:19 PM	--	Folder
	File	EulerOrientation.csv	Today 12:19 PM	11 KB	comm...values
	File	EulerStandardDeviation.csv	Today 12:19 PM	10 KB	comm...values
	File	RawSensors.csv	Today 12:19 PM	24 KB	comm...values
	File	Status.csv	Today 12:19 PM	14 KB	comm...values
	File	OrientusLog_13-02-14_16-12-25.anpp	Yesterday 4:12 PM	70 KB	Document

Illustration 2: Screenshot showing log file and log conversion folder



6 Views

The views menu contains a number of different options for viewing data from Orientus.




Illustration 3: Screenshot of Orientus Manager view menu

6.1 Device Information

Device information is mostly useful during technical support.




Illustration 4: Screenshot of Orientus Manager device information dialog

6.2 Status

Status shows Orientus's complete status as contained in the system state packet.




Illustration 5: Screenshot of Orientus Manager status dialog

6.3 Raw Sensors

Raw sensors shows the temperature calibrated raw sensor values.




Illustration 6: Screenshot of Orientus Manager raw sensors dialog

6.4 Orientation

Orientation shows Orientus's orientation and angular velocity.




Illustration 7: Screenshot of Orientus Manager orientation dialog



7 Configuration

The configuration menu contains a number of dialogs for the configuration of Orientus.




Illustration 8: Screenshot of Orientus Manager configuration menu

7.1 Sensor Ranges




Illustration 9: Screenshot of Orientus Manager sensor ranges dialog



7.2 Filter Options




Illustration 10: Screenshot of Orientus Manager filter options dialog

7.3 Packet Rates




Illustration 11: Screenshot of Orientus Manager packet rates dialog



7.4 Alignment Configuration




Illustration 12: Screenshot of Orientus Manager alignment dialog

7.5 Position

This dialog is used to set the position of Orientus. The position is used to update the world magnetic model and provide enhanced magnetic heading performance. For best performance through magnetic interference the position should be updated each time the unit is moved more than 50km from the previous position.




Illustration 13: Screenshot of Orientus Manager position dialog

7.6 Baud Rates

When changing baud rates, some windows machines are unable to function at the higher baud rates. It is recommended to test the baud rate first with the permanent box unticked. This way, if it is not possible to communicate at the higher baud rate, a power cycle can be used to revert to the previous baud rate.




Illustration 14: Screenshot of Orientus Manager baud rates dialog

7.7 GPIO Configuration




Illustration 15: Orientus Manager GPIO configuration dialog

7.8 Reset



Illustration 16: Screenshot of Orientus Manager reset dialog

8 Tools

The tools menu contains tools for performing procedures with Orientus.



Illustration 17: Screenshot of Orientus Manager tools menu

8.1 Terminal

The terminal is only used during specialised technical support with Advanced Navigation engineers.

8.2 Magnetic Calibration

The magnetic calibration dialog allows the user to perform magnetic calibration as well as view and modify the magnetic calibration values.




Illustration 18: Screenshot of Orientus Manager magnetic calibration dialog



8.3 Firmware Update

The firmware update dialog is used to update Orientus's firmware. Advanced Navigation firmware files have the extension .anfw.




Illustration 19: Screenshot of Orientus Manager firmware update dialog

8.4 Log Converter

This tool allows the user to convert Orientus log files into CSV and KML format that are readable by many programs.




Illustration 20: Screenshot of Orientus Manager log converter dialog



Information in this document is provided solely in connection with Advanced Navigation products. Advanced Navigation reserves the right to make changes, corrections, modifications or improvements, to this document, and the products and services described herein at any time, without notice.

All Advanced Navigation products are sold pursuant to Advanced Navigation's terms and conditions of sale. Purchasers are solely responsible for the choice, selection and use of the Advanced Navigation products and services described herein, and Advanced Navigation assumes no liability whatsoever relating to the choice, selection or use of the Advanced Navigation products and services described herein.

No license, express or implied, by estoppel or otherwise, to any intellectual property rights is granted under this document. If any part of this document refers to any third party products or services it shall not be deemed a license grant by Advanced Navigation for the use of such third party products or services, or any intellectual property contained therein or considered as a warranty covering the use in any manner whatsoever of such third party products or services or any intellectual property contained therein.

UNLESS OTHERWISE SET FORTH IN ADVANCED NAVIGATION'S TERMS AND CONDITIONS OF SALE ADVANCED NAVIGATION DISCLAIMS ANY EXPRESS OR IMPLIED WARRANTY WITH RESPECT TO THE USE AND/OR SALE OF ADVANCED NAVIGATION PRODUCTS INCLUDING WITHOUT LIMITATION IMPLIED WARRANTIES OF MERCHANTABILITY, FITNESS FOR A PARTICULAR PURPOSE (AND THEIR EQUIVALENTS UNDER THE LAWS OF ANY JURISDICTION), OR INFRINGEMENT OF ANY PATENT, COPYRIGHT OR OTHER INTELLECTUAL PROPERTY RIGHT.

UNLESS EXPRESSLY APPROVED IN WRITING BY TWO AUTHORIZED ADVANCED NAVIGATION REPRESENTATIVES, ADVANCED NAVIGATION PRODUCTS ARE NOT RECOMMENDED, AUTHORIZED OR WARRANTED FOR USE IN MILITARY, AIR CRAFT, SPACE, LIFE SAVING, OR LIFE SUSTAINING APPLICATIONS, NOR IN PRODUCTS OR SYSTEMS WHERE FAILURE OR MALFUNCTION MAY RESULT IN PERSONAL INJURY, DEATH, OR SEVERE PROPERTY OR ENVIRONMENTAL DAMAGE.

ADVANCED NAVIGATION PRODUCTS WHICH ARE NOT SPECIFIED AS "AUTOMOTIVE GRADE" MAY ONLY BE USED IN AUTOMOTIVE APPLICATIONS AT USER'S OWN RISK.

Resale of Advanced Navigation products with provisions different from the statements and/or technical features set forth in this document shall immediately void any warranty granted by Advanced Navigation for the Advanced Navigation product or service described herein and shall not create or extend in any manner whatsoever, any liability of Advanced Navigation.

Information in this document supersedes and replaces all information previously supplied.

© 2012 Advanced Navigation Pty Ltd - All rights reserved